

► Companies can choose between investments with different risks

- Companies can choose between investments with different risks
- Banks seek to provide incentives to choose investments with low risks

- Companies can choose between investments with different risks
- Banks seek to provide incentives to choose investments with low risks
- ► They do so by setting loan conditions

- Companies can choose between investments with different risks
- Banks seek to provide incentives to choose investments with low risks
- ► They do so by setting loan conditions, the loan rate

- Companies can choose between investments with different risks
- Banks seek to provide incentives to choose investments with low risks
- ▶ They do so by setting loan conditions, the loan rate and the loan size

- Companies can choose between investments with different risks
- Banks seek to provide incentives to choose investments with low risks
- ▶ They do so by setting loan conditions, the loan rate and the loan size

- ► If successful, companies obtain their return
- $\qquad \qquad \Pi_C^i = \pi_i \left(\left(1 + R_i \right) L \right)$

- ► If successful, companies obtain their return and repay the loan

- ▶ If successful, companies obtain their return and repay the loan
- $\Pi_C^i = \pi_i ((1 + R_i) L (1 + r_L) L)$
- $lackbox{ }$ Companies choose the low-risk investment if $\Pi_C^H \geq \Pi_C^L$

- If successful, companies obtain their return and repay the loan
- $\Pi_C^i = \pi_i ((1 + R_i) L (1 + r_L) L)$
- $lackbox{ }$ Companies choose the low-risk investment if $\Pi_C^H \geq \Pi_C^L$

$$\Rightarrow 1 + r_L \le 1 + \hat{r}_L = \frac{\pi_H(1 + R_H) - \pi_L(1 + R_L)}{\pi_H - \pi_L}$$

- If successful, companies obtain their return and repay the loan
- $\Pi_C^i = \pi_i ((1 + R_i) L (1 + r_L) L)$
- \blacktriangleright Companies choose the low-risk investment if $\Pi_C^H \geq \Pi_C^L$

$$\Rightarrow 1 + r_L \le 1 + \hat{r}_L = \frac{\pi_H(1 + R_H) - \pi_L(1 + R_L)}{\pi_H - \pi_L}$$

- ▶ Banks are repaid the loan if the company is successful

- ▶ Banks are repaid the loan if the company is successful, and repay deposits
- $\Pi_B^i = \pi_i (1 + r_L) L (1 + r_D) L$

- ▶ Banks are repaid the loan if the company is successful, and repay deposits
- $\Pi_B^i = \pi_i (1 + r_L) L (1 + r_D) L$
- ▶ The success rate of the company will depend on the loan rate they charge

- Banks are repaid the loan if the company is successful, and repay deposits
- $\Pi_B^i = \pi_i (1 + r_L) L (1 + r_D) L$
- ▶ The success rate of the company will depend on the loan rate they charge

$$\blacksquare \Pi_B = \left\{ \begin{array}{ll} \Pi_B^L & \text{if} \quad r_L \le \hat{r}_L \\ \Pi_B^L & \text{if} \quad r_L > \hat{r}_L \end{array} \right.$$


- Banks are repaid the loan if the company is successful, and repay deposits
- $\Pi_B^i = \pi_i (1 + r_L) L (1 + r_D) L$
- ▶ The success rate of the company will depend on the loan rate they charge
- $\blacksquare \Pi_B = \left\{ \begin{array}{ll} \Pi_B^L & \text{if} \quad r_L \le \hat{r}_L \\ \Pi_B^L & \text{if} \quad r_L > \hat{r}_L \end{array} \right.$
- Low loan rates will induce low risks

- Banks are repaid the loan if the company is successful, and repay deposits
- $\Pi_B^i = \pi_i (1 + r_L) L (1 + r_D) L$
- ▶ The success rate of the company will depend on the loan rate they charge
- $\blacksquare \Pi_B = \left\{ \begin{array}{ll} \Pi_B^L & \text{if} \quad r_L \leq \hat{r}_L \\ \Pi_B^L & \text{if} \quad r_L > \hat{r}_L \end{array} \right.$
- Low loan rates will induce low risks and high loan rates high risks


- Banks are repaid the loan if the company is successful, and repay deposits
- $\Pi_B^i = \pi_i (1 + r_L) L (1 + r_D) L$
- ▶ The success rate of the company will depend on the loan rate they charge
- $\blacksquare \Pi_B = \left\{ \begin{array}{ll} \Pi_B^L & \text{if} \quad r_L \leq \hat{r}_L \\ \Pi_B^L & \text{if} \quad r_L > \hat{r}_L \end{array} \right.$
- Low loan rates will induce low risks and high loan rates high risks




Copyright by Andreas Krause




Copyright O by Andreas Krause




Copyright O by Andreas Krause




Copyright by Andreas Krause




Copyright by Andreas Krause




Copyright O by Andreas Krause





Copyright (C) by Andreas Krause








Copyright O by Andreas Krause




















Banks do not increase loan rates above a threshold as this would induce companies to choose high-risk investments

- Banks do not increase loan rates above a threshold as this would induce companies to choose high-risk investments
- ▶ Banks ration loans as demand exceeds supply at this loan rate

- ▶ Banks do not increase loan rates above a threshold as this would induce companies to choose high-risk investments
- Banks ration loans as demand exceeds supply at this loan rate
- ⇒ Banks seeking large loans due to low loan rates may be rationed

- Banks do not increase loan rates above a threshold as this would induce companies to choose high-risk investments
- Banks ration loans as demand exceeds supply at this loan rate
- ⇒ Banks seeking large loans due to low loan rates may be rationed



This presentation is based on

Andreas Krause: Theoretical Foundations of Banking, 2025

Copyright © by Andreas Krause

Picture credits:

Cover: Bernard Spragg, NZ from Christchurch, New Zealand, CC0, via Wikimedia Commons, https://commons.wikimedia.org/wiki/File:Bank.of.China.Hong.Kong. (9532283389).jpg Back: Florian Lindner, CC BY 2.5 https://creativecommons.org/licenses/by/2.5 via Wikimedia Commons, https://commons.wikimedia.org/wiki/File:Hong.Kong.Panorama.at.night.jpg

Andreas Krause Department of Economics University of Bath Claverton Down Bath BA2 7AY United Kingdom

E-mail: mnsak@bath.ac.uk