



Value-at-risk

Outline

- Measuring risk
- Value-at-Risk
- Managing portfolio risk
- Discussion

■ Measuring risk

■ Value-at-Risk

■ Managing portfolio risk

■ Discussion

Limits to volatility as a risk measure

- ▶ Risk is the possibility of a loss
- ▶ Volatility does not only capture negative outcomes below the mean, but also positive outcomes above the mean
- ▶ A risk measure is needed that focuses exclusively on losses
- ▶ The risk measure should capture the size losses better than volatility, especially fat tails

Desirable properties of a risk measure

- ▶ A risk measure could be the reasonable amount that can be lost within a given time horizon
- ▶ What is reasonable will depend on the implications losses have and the risk aversion of the user
- ▶ The more severe the impact and the more risk averse the user is, the smaller the loss beyond what is reasonable should be
- ▶ Reporting risk as potential losses has the advantage that the result is intuitively understood by decision-makers

■ Measuring risk

■ Value-at-Risk

■ Managing portfolio risk

■ Discussion


Probability of large losses

- ▶ The Value-at-Risk is a statement that the loss will not exceed this amount with a probability of c over the next T time periods.
- ▶ Losses will only be larger than the Value-at-Risk with probability $1 - c$
- ▶ A loss needs to be defined relative to a benchmark, which could be the status quo (absolute loss) or the expected outcome (relative loss)
- ▶ In financial markets returns are small and for simplicity the relative loss is commonly used

Definition of Value-at-Risk

- ▶ Define a threshold such that the probability that the outcome is below this threshold is given by a certain value
- ▶ $Prob(V < \hat{V}) = 1 - c$
- ▶ The Value-at-Risk is then given as the difference between this threshold and the expected outcome
- ▶ $VaR = E[V] - \hat{V}$
- ▶ Value-at-Risk is the estimation of the $1 - c$ -quantile of the distribution of outcomes


Value-at-Risk as a quantile



Value-at-Risk for normal distributions

- ▶ If the distribution is normal, the $1 - c$ -quantile can be determined using the quantiles of the standard normal distribution
- ▶ The standard normal distribution needs to be adjusted by the standard deviation of outcomes and the amount invested
- ▶ $VaR = \alpha\sigma V_0$
- ▶ The choice of quantile will depend on the risk aversion of the investor
- ▶ The more risk averse an investor is, the lower the quantile to cover a wider range of possible losses

Quantiles with a normal distribution



- Measuring risk
- Value-at-Risk
- **Managing portfolio risk**
- Discussion

Impact of assets on portfolio risk

- ▶ Investors usually hold a portfolio of assets and using its standard deviation we obtain the Value-at-Risk: $VaR = \alpha \sigma_p V_0$

- ▶ Portfolio variance:
$$\begin{aligned}\sigma_P^2 &= \sum_{i=1}^N \sum_{j=1}^N \omega_i \omega_j \sigma_{ij} \\ &= \sum_{i=1}^N \omega_i^2 \sigma_i^2 + \sum_{i=1}^N \sum_{j=1, j \neq i}^N \omega_i \omega_j \sigma_{ij}\end{aligned}$$

$$\begin{aligned}\Rightarrow \frac{\partial \sigma_P^2}{\partial \omega_i} &= 2\omega_i \sigma_i^2 + 2 \sum_{j=1, j \neq i}^N \omega_j \sigma_{ij} \\ &= 2Cov \left[R_i, \omega_i R_i + \sum_{j=1, j \neq i}^N \omega_j R_j \right] \\ &= 2Cov[R_i, R_P] \equiv 2\sigma_{iP}\end{aligned}$$

Marginal Value-at-Risk

- ▶ We are interested in how the Value-at-Risk changes as the weight of assets in the portfolio changes

- ▶
$$\begin{aligned}\frac{\partial \frac{VaR}{V_0}}{\partial \omega_i} &= \alpha \frac{\partial \sigma_P}{\partial \omega_i} \\ &= \alpha \sigma_P \beta_i \\ &= \beta_i \frac{VaR}{V}\end{aligned}$$

- ▶ This expression is referred to as the marginal Value-at-Risk, ∂VaR_i
- ▶ If we change the weight of asset i by a small amount, the Value-at-Risk changes by ∂VaR_i

Changes to the Value-at-Risk of a portfolio

- ▶ If we change the weight more than marginally, we can use a linear approximation of the change
- ▶ $\Delta VaR_i = \partial VaR_i V \Delta \omega_i = \beta_i \Delta \omega_i VaR$
- ▶ The total change in the Value-at-Risk is equal to the sum of the changes for each individual asset
- ▶ $\Delta VaR = \sum_{i=1}^N \Delta VaR_i = VaR \sum_{i=1}^N \beta_i \Delta \omega_i$
- ▶ If we only rearrange the weights, the total changes in the weights must be zero:
 $\sum_{i=1}^N \Delta \omega_i = 0$

Changing portfolio risk

- ▶ To reduce the risk of a portfolio, reduce the weight of those assets with high marginal Value-at-Risks, high β_i , and increase those with low marginal Value-at-Risk, low β_i
- ▶ Reducing the weight of an asset with a high β_i reduces the Value-at-Risk considerably and increasing the weight of an asset with low β_i increases it by less, leading to a reduction in the Value-at-Risk
- ▶ The larger the difference between these two assets is, the bigger the impact on the Value-at-Risk
- ▶ For two assets the solution is unique, but for more assets many solutions exist
- ▶ Not always is it desirable or possible to change the weight of an asset, strategic investment decisions might become relevant
- ▶ The marginal Value-at-Risk gives indication which assets to choose most efficiently

■ Measuring risk

■ Value-at-Risk

■ Managing portfolio risk

■ Discussion


The benefits of using Value-at-Risk

- ▶ Value-at-Risk can be used to measure risk in an intuitive way by focussing exclusively on losses
- ▶ It provides a framework in which risks of individual assets in a portfolio can be assessed
- ▶ Portfolios can be re-arranged to meet risk limits and the marginal Value-at-Risk can be used to identify assets that should change weights

Limits of Value-at-Risk

- ▶ You have a single loan worth £100m with a probability of default 0.9%, the amount lost in case of default is the full amount
- ⇒ 99% VaR: £-0.9m
- ▶ Suppose now we have two loans of £50m each with the same default rate and defaults are independent
- ▶ $\text{Prob}(1 \text{ default occurs}) = 2 \times \text{Prob}(\text{default}) (1 - \text{Prob}(\text{default})) = 0.017838$
- ▶ $\text{Prob}(2 \text{ defaults occur}) = \text{Prob}(\text{default})^2 = 0.000081$
- ⇒ 99% VaR: £49.1m
- ⇒ The VaR increases with diversification

Diversification increasing Value-at-Risk





Copyright © by Andreas Krause

Picture credits:

Cover: Tobias Deml, CC BY-SA 4.0 <https://creativecommons.org/licenses/by-sa/4.0>, via Wikimedia Commons, https://upload.wikimedia.org/wikipedia/commons/2/26/Gaming-Wall-Street_BTS_Prodigium-266.jpg

Back: Michael Vadon, CC BY 2.0 <https://creativecommons.org/licenses/by/2.0/>, via Wikimedia Commons, [https://upload.wikimedia.org/wikipedia/commons/9/97/Manhattan\(NYC-New-York-City\)Skyline\(31769153946\).jpg](https://upload.wikimedia.org/wikipedia/commons/9/97/Manhattan(NYC-New-York-City)Skyline(31769153946).jpg)

Andreas Krause
Department of Economics
University of Bath
Claverton Down
Bath BA2 7AY
United Kingdom

E-mail: mnsak@bath.ac.uk